

# Chapter 1

## Differential Geometry

### 1.1 Tensors

A **tensor** is a mathematical object that directly represents a physical quantity. Tensors of the same type can be added, and multiplied by a scalar, in the usual way. Scalars and vectors are tensors, but many physical quantities are some other type of tensor.

A **scalar** is a tensor that behaves like a number. Examples of spatial<sup>1</sup> scalars are time  $t$ , energy  $E$  and electric potential  $\phi$ . Examples of spacetime scalars are proper time  $\tau$ , mass  $m$  and charge  $q$ .

#### 1.1.1 Vectors and covectors

A **vector** is a tensor that behaves like an arrow. Their properties inspire the vector



Figure 1.1.1: A vector.

space axioms of mathematics. A scalar times a vector is a vector and the sum of two vectors is a vector, see Figure 1.1.2. Examples of vectors are displacement  $\vec{dx}$ , velocity



Figure 1.1.2: The sum of two vectors is a vector.

---

<sup>1</sup>Physical quantities may be one type of tensor with respect to one space but another type of tensor with respect to another space. For example, a displacement in time is a scalar with respect to space but a vector with respect to time. Unless otherwise specified, the space can be assumed to be space, or spacetime in the context of relativity.

$$\vec{v} \equiv \frac{d\vec{x}}{dt} \tag{1.1.1}$$

and acceleration

$$\vec{a} \equiv \frac{d\vec{v}}{dt} \tag{1.1.2}$$

A **covector** or **one-form** is a tensor that behaves like the local linearized form of contour lines or the crests of a wave, see Figure 1.1.3. A scalar times a covector




Figure 1.1.3: A covector.

is a covector and the sum of two covectors is a covector, see Figure 1.1.4. Examples




Figure 1.1.4: The sum of two covectors is a covector.

of covectors are the gradient of a scalar field  $\underline{\nabla}\phi$ , wave “vectors”  $\underline{k}$ , electric field and magnetic “vector” potential

$$\underline{E} = -\underline{\nabla}\phi - \frac{\partial \underline{A}}{\partial t} \tag{1.1.3}$$

momentum

$$\underline{p} = \hbar \underline{k} \tag{1.1.4}$$

and force

$$\underline{F} = q \underline{E} \tag{1.1.5}$$

or

$$\underline{F} = \frac{d\underline{p}}{dt} \tag{1.1.6}$$

A vector can be **contracted** with a covector to give a scalar

$$\vec{v} \cdot \underline{\omega} = \text{scalar} \tag{1.1.7}$$

corresponding to the number of covector planes crossed by the vector, with sign given by the relative orientations of the vector and covector, see Figure 1.1.5. For example, a




Figure 1.1.5: A **vector** contracted with a **covector** gives a **scalar**.

displacement contracted with the gradient of a scalar field gives the change in the scalar field

$$d\vec{x} \cdot \underline{\nabla}\phi = d\phi \tag{1.1.8}$$

and power equals force contracted with velocity

$$P = \underline{F} \cdot \vec{v} \tag{1.1.9}$$

Comparing vectors and covectors, the magnitude of a vector is given by its length, while the magnitude of a covector is given by the density of its planes. The direction of a vector is along its length (intrinsically oriented), while the direction of a covector is normal to its planes (extrinsically oriented) in the sense that  $\underline{n} \cdot \vec{v} = 0$  for any vector  $\vec{v}$  lying in the plane of the covector  $\underline{n}$ . Thus, a vector is an intrinsically oriented dimension one plane element, while a covector is an extrinsically oriented codimension<sup>2</sup> one plane density.

### 1.1.2 Abstract index notation

The notation  $\vec{v}$  and  $\underline{\omega}$  works well for vectors and covectors but is inadequate for more general tensors. Instead, we will use the **abstract index notation** in which a vector  $\vec{v}$  is written  $v^a$  and a covector  $\underline{\omega}$  is written  $\omega_a$

$$\vec{v} \leftrightarrow v^a \quad , \quad \underline{\omega} \leftrightarrow \omega_a \tag{1.1.10}$$

The abstract index **a** denotes the tensorial nature of the quantity by its position and does not take specific values. A contraction is denoted by repeated indices

$$\underline{\omega} \cdot \vec{v} \leftrightarrow \omega_a v^a \tag{1.1.11}$$

A **tensor** can have an arbitrary number of vector and covector indices  $T_{\underline{cd}\dots}^{\underline{ab}\dots}$ .

A tensor  $T_{\underline{ab}}$  can be decomposed into **symmetric** and **antisymmetric** parts

$$T_{\underline{ab}} = T_{(\underline{ab})} + T_{[\underline{ab}]} \tag{1.1.12}$$

where round brackets denote the symmetric part

$$T_{(\underline{ab})} = \frac{1}{2} (T_{\underline{ab}} + T_{\underline{ba}}) \tag{1.1.13}$$

and square brackets denote the antisymmetric part

$$T_{[\underline{ab}]} = \frac{1}{2} (T_{\underline{ab}} - T_{\underline{ba}}) \tag{1.1.14}$$

<sup>2</sup>Codimension  $d$  is dimension  $D - d$  where  $D$  is the dimension of the space.

### 1.1.3 Metric

The **metric**  $g_{ab}$  and inverse metric  $g^{ab}$  define lengths and angles in a space. They are symmetric tensors

$$g_{ab} = g_{ba} \quad , \quad g^{ab} = g^{ba} \quad (1.1.15)$$

and related by

$$g^{ab} g_{bc} = \delta_c^a \quad (1.1.16)$$

where the identity tensor  $\delta_{\mathbf{b}}^{\mathbf{a}}$  has the property

$$\delta_{\mathbf{b}}^{\mathbf{a}} v^{\mathbf{b}} = v^{\mathbf{a}} \quad , \quad \delta_{\mathbf{a}}^{\mathbf{b}} \omega_{\mathbf{b}} = \omega_{\mathbf{a}} \quad (1.1.17)$$

and similarly for other tensors.

The metric gives the **inner product** of vectors and covectors

$$\vec{u} \cdot \vec{v} = g_{ab} u^a v^b \quad , \quad \underline{\omega} \cdot \underline{\sigma} = g^{ab} \omega_a \sigma_b \quad (1.1.18)$$

Note that these inner products depend on the metric, in contrast to the contraction of a vector with a covector.

The metric converts vectors into covectors and vice versa

$$\begin{aligned} v_{\mathbf{a}} &= g_{ab} v^{\mathbf{b}} \quad , \quad v^{\mathbf{a}} = g^{\mathbf{ab}} v_{\mathbf{b}} \\ \omega^{\mathbf{a}} &= g^{\mathbf{ab}} \omega_{\mathbf{b}} \quad , \quad \omega_{\mathbf{a}} = g_{ab} \omega^{\mathbf{b}} \end{aligned} \quad (1.1.19)$$

For example, the traditional vector representation  $\vec{E}$  of the electric field  $\underline{E}$  is

$$E^{\mathbf{a}} = g^{\mathbf{ab}} E_{\mathbf{b}} \quad (1.1.20)$$

More generally, the metric can **raise** or **lower indices** on any tensor <sup>3</sup>

$$T^{\mathbf{a}}_{\mathbf{b}} = g_{bc} T^{\mathbf{ac}} \quad (1.1.21)$$

---

<sup>3</sup>It is important to maintain the horizontal position of the indices if the tensor is not symmetric since  $T^{\mathbf{a}}_{\mathbf{b}} = g_{bc} T^{\mathbf{ac}} \neq g_{bc} T^{\mathbf{ca}} = T_{\mathbf{b}}^{\mathbf{a}}$  if  $T^{\mathbf{ac}} \neq T^{\mathbf{ca}}$ .